



TRACELINK UNIVERSITY

Home

Resources

TraceLink University

Intro to event-driven APIs

Before referring to the API portion of this guide, users that might integrate via API should work with their TraceLink implementation team to help configure their system and receive the appropriate endpoints and authentication information.

Event-driven APIs

The Opus Platform accepts all APIs through one exposed `/api/events` endpoint per environment using the POST HTTP method regardless of the operation being performed or the object being operated upon. This is unlike a traditional RESTful Web service, which exposes multiple endpoints where users can perform operations with HTTP methods (e.g. GET, POST, PUT, etc.). The app that handles the request and the objects affected by the request are determined based on the contents of the header section of the request body.

These event-driven APIs can be used to integrate the TraceLink app with your company's internal systems (e.g. enterprise resource planning system, warehouse management system).

Request header

The request header contains the metadata associated with the API request. All API calls to the Opus Platform must include the following key-value pairs in the request

header:

- **Content-Type** - The media type for the message. Valid value is `application/json`.
- **Authorization** - The authorization token required to connect to the platform and environment.

Request body

The request body contains the message routing and handler information as well as the contents of the request. All API requests submitted to the Opus Platform must include the following header and payload elements:

- **header** - Specifies the event type of the request and the app that will receive the request. This must include the following parameters:
 - **headerVersion** - The header version. Valid value is `1`.
 - **eventName** - The fully qualified name of the event that will be triggered by the request. This is typically formatted as `[app-name]:[event-name]:[version]` (e.g. `agile-process-teams:add-incident:v1`).
 - **appName** - The application that owns the event (e.g. `agile-process-teams`).
 - **ownerId** - The identifier for the company that is providing the app.
 - **dataspace** - The dataspace within the environment that the request call is being made. Valid value is `default`.
- **payload** - Includes the contents of the request.

Authorization

Users are granted authorization to the Opus Platform through an API token. The users need to generate an API token prior to sending an API request in order to identify a username (an API key) and password (an API secret). A valid username and password must be included in the headers to process the API request

successfully. This username and password does not expire, and it can be used in all API calls.

HTTP response status code

TraceLink APIs use standard response codes to indicate whether an HTTP request was successful. Response status codes may include, but are not limited to, the following:

Successful response

200	OK. The request was successful.
-----	---------------------------------

Redirect message

307	Temporary Redirect. The client must get the requested resource at another URI with the same HTTP method that was used in the prior request.
-----	---

Client error status codes

400	Bad Request. The server could not understand the request due to invalid syntax.
401	Unauthorized. The client is unauthenticated, not allowed access, and should re-request credentials.
403	Forbidden. The request is valid and the client is authenticated, but the client is not allowed access rights to the content for any reason.
404	Not Found. The server cannot find the requested item. This can also mean that the endpoint is valid but the resource does not exist.

Server error status codes

500	Internal Server Error. The server has encountered an unknown error.
502	Bad Gateway. The server is working as a gateway to handle the request and received an invalid response.
503	Service Unavailable. The server is not ready to handle the request.
504	Gateway Timeout. The server is acting as a gateway and cannot get a response in time.

How to use this guide

Read the guidelines table

A guidelines table contains element requirements for a message:

Element	Type	Description
Header		Required. The request header.
headerVersion	Integer	Required.Required. The version identifier for the request. Valid value is 1.
eventName	String	Required. The fully qualified name of the request event. Valid value is NEED INFO
ownerId	String	Required. The identifier for the Owner company associated with the request.
isErr	String	Required. Indicates whether the request was successful. Valid values: <ul style="list-style-type: none"> • true - The call was successful. • false - The call was not successful. The errCode and errMsg fields provide error information for troubleshooting.
errCode	String	Required. The status code of the response.
errMsg	String	Conditionally required if the call is unsuccessful. The message associated with the error code (e.g. "Process Type is required.").
licensePlate	String	Required. The unique identifier for the message instance.
exceptionName	String	(missing or bad snippet)
Payload		Required. The request body.
commentId	String	Conditionally required if the call is successful. The identifier for the added comment.

Element


This column indicates the source/element name included in the API call.

Type

This column indicates the element's data format type (e.g. String, Integer, Boolean, Date, or Time).

Description

This column indicates whether the element is required for the message and provides a brief description of the element, including any relevant notes (e.g. country requirements, formatting notes, etc.).

 Hover over a footnote to display the data input sample for that Data Element. If using the printed version of the document, refer to the matching footnote at the bottom of the table.

Read the message example

Sample requests and responses, where relevant, are provided for each message.

Below is a Copy Direct Supplier Incident request example:

```
{
  "header": {
    "headerVersion": 1,
    "eventName": "agile-process-teams:copy-direct-supplier-incident:v2",
    "ownerId": "94f94f37-2772-4b39-8041-9c2dcfcfff82",
    "processNetworkId": "945feb8e-09a7-4fef-9a8a-b3c5b56f87d",
    "appName": "agile-process-teams",
    "dataspace": "default"
  },
  "payload": {
    "id": "fd04dd70-c162-43ef-8118-539ca01de471",
    "createdByPartner": false,
    "aptBusinessObjectSummary": "Shipment Damage",
    "copyGeneralInfo": true,
    "copyPartnerInfo": false,
    "copyMaterialInfo": true,
    "copyImpactInfo": false,
    "copyReferenceIds": false,
    "copyRelatedProcesses": true
  }
}
```

Related Content



Modify your account

Modify your profile, define app settings, and enable inbox messages and notifications.

[View More](#)



Switch companies or environments

The OPUS Ensemble user experience allows you to switch between companies or environments that you have access to with the same user account (identified by an email)

without logging into a separate URL.

View More



Navigate to help documentation and support

Select the Help Center icon in the header to access the one-stop-shop help center for everything related to the network you are currently within (e.g.

View More